



What is the driver for?

The driver can be installed to recognize the stand-alone USB keys. These keys are mostly black or purple as shown in the images.

By default, these drivers are installed during the installation of SCIA Engineer if the user has chosen 'stand-alone license' during the setup. In some cases, it is necessary to install the driver separately.

How to do this?

Follow [the link](#) to the page of the key provider. This ensures you can download and install the latest version. Pick the "Sentinel Protection Installer" and execute the setup in the zipped file.

SafeNet is now Gemalto [Contact Us](#) English Search

gemalto
security to be free

HOME OUR SOLUTIONS OUR COMPANY RESOURCES SUPPORT PARTNERS

Sentinel Drivers

Support & Downloads

- Technical Support
- Security Updates
- Downloads and Developer Kits
- SafeNet Service Portal
- Government Customers Technical Support
- Beta Programs
- SafeNet Authentication Service Support

Contact Us

- Request Information
- Contact Sales Now
- Join our SM Mailing List
- Join our DP Mailing List
- Office Locations
- Our SafeNet Blogs

Sentinel Drivers

[Click Here](#) for the latest End User Troubleshooting Guide. [CLICK HERE FOR ALL SENTINEL DOWNLOADS](#)

Windows Driver & Utilities

Driver Name	Version	Products	OS	Includes
Sentinel Protection Installer	v7.6.8	Sentinel SuperPro, UltraPro, SentinelPro, SHK.	Microsoft Windows XP (32-bit and 64-bit), Windows Server 2003 (32-bit and 64-bit), Windows Vista (32-bit and 64-bit), Windows Server 2008 (32-bit and 64-bit), Windows Server 2008 R2 (64-bit), Windows 7 (32-bit and 64-bit), Windows 8 (32-bit and 64-bit), Windows Server 2012 (64-bit), and Windows 8.1 (32-bit and 64-bit).	Sentinel USB driver version 7.5.9.0 Sentinel Parallel driver version 7.5.0.2 Sentinel Protection Server version 7.6.4.0 Sentinel Keys Server version 1.3.5.0 Sentinel Security Runtime version 1.0.1.0
Sentinel Driver	v7.5.9	Sentinel SuperPro, UltraPro, SentinelPro, SHK.	Windows XP/Server 2003/2008/2012/Vista & Windows 7, 8 and 8.1 (32 bit and 64 bit)	Sentinel USB driver version 7.5.9.0 Sentinel Parallel

Note: if you wish to use old software (for example **ESA-PT** or **ESA-PRIMA WIN**), then choose 'Custom' during installation and explicitly indicate that you do not want to install the "Parallel Driver".

